



Wordy Stuff	Protocols	Results	Code available at: https://lunet-my.sharepoint.com/:f/r/personal/mmct_lunet_lboro_ac_uk/Documents/2021%20Internship%20-%20B%20Sargeant/Completed%20Macro_Bread_Analysis?csf=1&web=1&e=Dbk3m5
	Data Analysis Optimum		


Image Analysis – Overview of Analysis Code



Wordy Stuff	Protocols	Results
	Data Analysis Optimum	

Image Analysis (Fiji)

Code available at: https://lunet-my.sharepoint.com/:f:/t/personal/mmct_lunet_lboro_ac_uk/Documents/2021%20Internship%20-%20B%20Sargeant/Completed%20Macro Bread Analysis?csf=1&web=1&e=Dbk3m5



Required Add-ons - As well as downloading Fiji, additional plug-ins are required:


- **Install Bread Analysis Macros:** Copy the whole Complete Bread Analysis Marco folder into the local Fiji program files (ie. C:\Program Files\Fiji.app\plugins) > Restart Fiji
- Activate the **Bar**, **MorphotLibJ** and **Results_to_Excel** optional plug-ins. Open Fiji > Help > Updates > Manage update Sites > Check BAR, IJPB-plugins and ResultsToExcel > Close > Apply Changes > Close > Restart Fiji




Test 5 Power 0.5 Location 1+2.jpg
(1000x758 pixels)



T5_Pw0-5_Loc_1+2.tif
(80x96 mm)



It is optional to run this code as a batch process (folder), individually (open in Fiji and run *_All macro), or run analysis step-by-step (open in Fiji and run *0, *1, *2, *3, *4).
 * All variations of the code can be ran – Normal or Ring, and Original or Triangle.



* Ring setting will measure the middle hole and them remove it from the analysis.
 ** Triangle Analysis will use the Triangle thresholding method, instead of the original Minimum thresholding method. This is a common method to successfully run analysis on images that produce and error during the first run


Wordy Stuff

Protocols

Data Analysis | Optimum



Results

Image Analysis - Output



Once Analysis has been completed, the folder with the test images will be filled with sub-folders. Each subfolder is contains the results for one image and is named after that image.

All results are also saved to one document, in the Desktop. This must be coped to this folder before data analysis




NAME: Original File Input

- *_Area-Distribution: Plot of Frequency against Area
- *_Area-Map: Superposed colour map denoting the area of each pore
- *_Area-Map-Blank: Image of pores, with colour representing the Area
- *_Border: Image with Minimum Thresholding applied, used to identify the outer perimeter
- *_Circularity-Distribution: Plot of Frequency against Circularity
- *_Circularity-Map: Superposed colour map denoting Circularity
- *_Circularity-Map-Blank: Image pores, with colour representing Area
- *_Cropped: 8bit image with the outer perimeter (*_Border) used to crop the background
- *_Crust: Image after isolating the blue intensity and contrast local threshold. This should show the crust of the product
- *_Crust-Summary: Table of *_Crust average measurements – minor axis best represents crust thickness
- *_Feret-Angle-Map: Superposed colour map denoting the Feret's Angle
- *_Feret-Angle-Map-Blank: Image of pores, with colour representing Feret's Angle

- *_Feret-Length-Distribution: Plot of Frequency against Feret's Length
- *_Feret-Length-Map: Superposed colour map denoting Feret's Length
- *_Feret-Length-Map-Blank: Image pores, with colour representing Feret's Length
- *_Global-Measurements: Table of measurements recoded from the whole of the slice (withing perimeter identified by *_Border)
- *_Greyscale: 8bit image
- *_Particles: Superposed outlines of identified pores
- *_Porosity-Map: Heat map of the global porosity
- *_Porosity-Map-Contours: Map showing contours of global porosity
- *_Results: Table of measurements taken from each pore. These results were also copied into one document, saved to the desktop, collating all results in one file.
- *_Thresholded: Image after Bernsen Local Thresholding, 'kill borders' and 'fill holes' from MorphotLibJ Plug-in



Wordy Stuff	Protocols		Results
	Image Analysis	Optimum	

Data Analysis (Excel)



Requirements


- Results Document must be saved as a macro-enabled (".xlsm") file.
- Save file in the results folder, with individual results in the subfolders
- Add the Developer tab to the menu, or access VB code window using Alt + F11.
- Set Trust Centre to allow macros and VBA objects:
 - Open Excel > File > Options > Trust Centre > Trust Center Settings... > Macro Settings
 - Ensure the Check box "Trust access to the VBA project object model" is checked
 - And Enable VBA Macros




Code available at: https://lunet-my.sharepoint.com/:f:/r/personal/mmct_lunet_lboro_ac_uk/Documents/2021%20Internship%20-%20B%20Sargeant/Completed%20Macro_Bread_Analysis?csf=1&web=1&e=Dbk3m5

Wordy Stuff	Protocols		Results
	Image Analysis	Optimum	

Optional Excel Analysis



Code available at: https://lunet-my.sharepoint.com/:f:/r/personal/mmct_lunet_lboro_ac_uk/Documents/2021%20Internship%20-%20B%20Sargeant/Completed%20Macro_Bread_Analysis?csf=1&web=1&e=Dbk3m5



Version Tracker

Version	Updated	Changes Made
Beta	06/2021	First completion of the Image analysis
Version 1	07/2021	Image analysis adjusted to repair bugs, found during use. Also includes completed Excel data analysis
Version 2	08/2021	User interface made more user friendly and code more universal, to mend bugs found during use.
Version 3	09/2021	Code reduced to aid licencing, Name prep changed to remove naming restrictions (auto replace), additional input types, scaling options, min circularity set to 0.1 [no pores are below 0.1] and re-written steps to make easy use